

Integrator Configuration

The configuration file for Integrator is located at
\\tomcat\webapps\etlserver\config\config.xml (Windows) or
/opt/jedox/ps/tomcat-etl/webapps/etlserver/config/config.xml (Linux).
The parameters for configuration are described below. After making
any changes to the file, the Tomcat service must be restarted.

Important: configuration files are replaced when Jedox software is updated. You should therefore maintain a backup of your configuration files, so you can replace them after an update.

Parameter	Description of parameter value	Default value	Type
logFileSize	Maximum size of one etlserver log file in bytes, KB, MB, or GB	10MB	string
logBackupIndex	Maximum number of etlserver log files to keep	20	integer
maxParallelReadExecutions	Maximum number of parallel running integrator executions	7	integer
maxParallelWriteExecutions	Maximum number of parallel running integrator jobs or loads	5	integer
maxQueuedExecutions	Maximum number of executions that can be queued	42	integer
removeWriteExecutions	Time (in hours) after which old job and load executions are removed from the integrator monitor	720 (30 days) *	integer
removeReadExecutions	Time (in hours) after which old executions are removed from the integrator monitor	168 (7 days)	integer
removeTempExecutions	Time (in hours) after which temporary executions are removed from the integrator monitor	1	integer

*in Jedox version 2019.1 and earlier, the default setting was 2400 (100 days)